

NovicoSoft Trade Manager

Installation Guide


Software Licensing Terms

Before you install NovicoSoft Trade Manager, you must accept the software licensing terms. Read the license agreement LICENSE.TXT included in the NovicoSoftTradeManager.zip.

Installation Procedure

NovicoSoft Trade Manager consists of a MetaTrader EA and associated MetaTrader Template that need to be copied within your MetaTrader installation. To install NovicoSoft Trade Manager, please follow the steps as below:

1. **Download** the NovicoSoftTradeManager.zip file from <http://NovicoSoft.com>.
2. **Extract** the files in NovicoSoftTradeManager.zip to your local directory. The following files will be extracted:
 - LICENSE.txt
 - experts\NovicoSoftTradeManagerEA.ex4
 - templates\NovicoSoftTradeManager.tpl
 - documents\Installation Guide.pdf
 - documents\User Guide.pdf
3. **Locate** the MetaTrader data folder. This is the folder where the MetaTrader terminal stores its data. Start your MetaTrader 4 platform. Select menu File in the top right hand corner and choose “Open Data Folder”, as below:



The list of MetaTrader data folders will be seen as below:

<input type="checkbox"/> Name	Date modified	Type	Size
config	18/01/2016 9:34 AM	File folder	
history	15/01/2016 8:30 PM	File folder	
logs	18/01/2016 2:02 PM	File folder	
MQL4	15/01/2016 8:02 PM	File folder	
profiles	17/01/2016 10:43 PM	File folder	
templates	17/01/2016 8:50 PM	File folder	
tester	15/01/2016 8:03 PM	File folder	
origin.txt	15/01/2016 8:02 PM	Text Document	1 KB

4. Copy extracted file **experts\NovicoSoftTradeManagerEA.ex4** to the MetaTrader data folder **MQL4\Experts**.
5. Copy extracted file **templates\NovicoSoftTradeManager.tpl** to the MetaTrader data folder **templates**.
6. Close MetaTrader 4 platform and **Start** again ...
7. To use NovicoSoft Trade Manager for a MetaTrader chart, select the **NovicoSoftTradeManager** template from the list of available chart templates.

Note: The NovicoSoft trade manager display can be zoomed in or out to make it larger or smaller as required. Press F7 to bring the NovicoSoft Trade Manager EA inputs. Update the value of input variable “DisplayZoomPercent” to zoom in (set value > 100) or out (set value < 100).

The display font can also be changed by updating the value of input variable “DisplayFontSize”.

More Information

Please read the **User Guide** for detailed description of the features and usage of NovicoSoft Trade Manager.

License Information

Trial License

NovicoSoft Trade Manager includes a copy of trial license that allows you to use it for a limited amount of time.

Full License

If you wish to continue using NovicoSoft Trade Manager beyond the trial period, please visit <http://NovicoSoft.com> to purchase a full license.

Help & Support

If you need any help with installation or usage for the NovicoSoft Trade Manager during the trial period or after purchase, please feel free to contact support at <http://NovicoSoft.com>